USB Install Astaro Firewall (UTM)

Creating Your Own Sophos UTM Bootable USB Installation Drive

Installing Sophos UTM from a boot CD is straightforward and works well. The only problem with this old school method is

that Sophos UTM appliances do not ship with optic drives, and this is true for most modern hardware.

Most current operating systems can be installed from USB (Windows, OSX, Linux, etc) and it is often the preferred method because

these OS installers are aware that they are installing from USB.

Sophos provide a USB installation option called the <u>Smart Installer</u> for UTM hardware appliances,

but this is a special USB drive that emulates a CD, essentially working around the issue.

This article steps you through the process of preparing and creating your own Sophos UTM bootable USB installation drive.

Please note that since this is a **workaround it is not a supported method by Sophos**. It is handy for building and rebuilding your home and test equipment but for your serious production

hardware please follow the official Sophos recommended method of attaching an external optical drive.

Step 1. Download the Sophos UTM ISO

Download the latest version of the Sophos UTM images from https://www.sophos.com/en-us/support/utm-downloads.aspx

There are two options when downloading the ISOs. One for hardware appliances and another for software appliances.

If you have a physical Sophos appliance use the first option, if you are building your own on a virtual machine or PC,

use the second option.

Step 2. Download and run Rufus

Rufus is a USB utility that allows you to create bootable USB drives from ISO images, and it is available from http://rufus.akeo.ie. There are a number of similar utilities available which you should be able to use if you prefer.

Pagina 1/5

- 1. The executable does not need to be installed. Simply run the exe as an administrator on your system.
- 2. In the **Format Option** section set the **Create a bootable disk using** to **ISO** and select the Sophos UTM ISO downloaded in step 1.
- 3. Click **Start** and accept the warning that the USB drive will be erased

The process take a few minutes and will notify you when it has completed.

Step 3. Boot and Build from USB

Here is the theory of what happens next. When the system boots from the USB drive it will be running

an installation subset version of Linux. This version runs completely in RAM.

For it to make use of files on the USB drive, the drive needs to be mounted. To do this we are going to switch between the installer

and a console session. We will use the console the mount the USB drive, making the files available,

and then switch back to the installer and continue from there.

Insert your USB drive into your device, in my case a Dell PC, power it on and invoke the boot selector by pressing **F12**

and then selecting the USB drive option.

Depending on the hardware, you may find it automatically boots from USB or you might have to access the BIOS

and set it as the preferred boot device.

This can normally be accessed by pressing the **Del** or **F2** key during POST.

The Sophos UTM installer should start and display the black Welcome screen. Press **Enter** to start the installation.

At the blue Introduction Screer	press Alt + F2.	This will switch	you to a console screen.
---------------------------------	-----------------	------------------	--------------------------

Mount your USB drive with the following command:

mount /dev/sdb1 /install

Press **Alt + F1** to switch back to the installer and carry on with the installation. If you run into an installation error, see the troubleshooting section below.

That's all there is to it! Once the installation finishes you can remove the USB drive and reboot.

Conclusion

You don't have to run around trying to find writable CD's or USB optical drives to build a physical Sophos UTM device.

You also don't have use the Sophos UTM Smart Installer USB drive. Although, if you are routinely building Sophos UTMs from scratch, it might be worth the convenience. For more details on the Smart Installer check out

http://www.sophos.com/en-us/support/utm-downloads/utm-smart-installer.aspx

Troubleshooting

If you are reading this it means you probably ran into an installation error. If you do not explicitly mount the USB drive as described, you may receive this error during the 'formatting' stage:

install.tar wasn't found on the installation media

The installation expects the install.tar file to be located in:			
/install/install.tar			
You can check this by switching back to the console with Alt + F2 and using			
cd /install/install			
Is			
It should list the following items:			
build; install.md5; install.tar; rpm			
If this error occurs, it is most likely that your USB device was not detected as /dev/sdb1. To verify this you can use the following command			
dmesg grep sd			
Look for your usb device in the list, it should show the device name and size. Change the mount command to reference the correct sdx1 device id. For example, instead of			
mount /dev/sdb1 /install			
mount /dev/sdc1 /install			
use something like:			
mount /dev/deviceid install Pagina 4 / 5 © 2025 diode <info@ictweetjes.nl> 30-09-2025 00:36</info@ictweetjes.nl>			

 $URL: \ https://www.ictweetjes.nl/faq/content/14/32/nl/usb-install-astaro-firewall-utm.html$

Unieke FAQ ID: #1031

Auteur: diode

Laatst bijgewerkt:28-09-2020 15:55