

Cisco

How to Configure a Cisco Layer 3 switch-Inter VLAN Routing

[Cisco L2 Switch](#) (same configuration for both switches)

! Create VLANs 10 and 20 in the switch database

```
Layer2-Switch# configure terminal
```

```
Layer2-Switch(config)# vlan 10
```

```
Layer2-Switch(config-vlan)# end
```

```
Layer2-Switch(config)# vlan 20
```

```
Layer2-Switch(config-vlan)# end
```

! Assign Port Fe0/1 in VLAN 10

```
Layer2-Switch(config)# interface fastethernet0/1
```

```
Layer2-Switch(config-if)# switchport mode access
```

```
Layer2-Switch(config-if)# switchport access vlan 10
```

```
Layer2-Switch(config-if)# end
```

! Assign Port Fe0/2 in VLAN 20

```
Layer2-Switch(config)# interface fastethernet0/2
```

```
Layer2-Switch(config-if)# switchport mode access
```

```
Layer2-Switch(config-if)# switchport access vlan 20
```

```
Layer2-Switch(config-if)# end
```

! Create Trunk Port Fe0/24

```
Layer2-Switch(config)# interface fastethernet0/24
```

```
Layer2-Switch(config-if)# switchport mode trunk
```

```
Layer2-Switch(config-if)# switchport trunk encapsulation dot1q
```

```
Layer2-Switch(config-if)# end
```

-

[Cisco Layer 3 Switch](#)

! Enable Layer 3 routing

```
Layer3-Switch(config) # ip routing
```

! Create VLANs 10 and 20 in the switch database

```
Layer3-Switch# configure terminal
```

```
Layer3-Switch(config)# vlan 10
```

```
Layer3-Switch(config-vlan)# end
```

Cisco

```
Layer3-Switch(config)# vlan 20  
Layer3-Switch(config-vlan)# end
```

! Configure a Routed Port for connecting to the ASA firewall

```
Layer3-Switch(config)# interface FastEthernet0/48  
Layer3-Switch(config-if)# description To Internet Firewall  
Layer3-Switch(config-if)# no switchport  
Layer3-Switch(config-if)# ip address 10.0.0.1 255.255.255.252
```

! Create Trunk Ports Fe0/47 Fe0/46

```
Layer3-Switch(config)# interface fastethernet0/47  
Layer3-Switch(config-if)# switchport mode trunk  
Layer3-Switch(config-if)# switchport trunk encapsulation dot1q  
Layer3-Switch(config-if)# end
```

```
Layer3-Switch(config)# interface fastethernet0/46  
Layer3-Switch(config-if)# switchport mode trunk  
Layer3-Switch(config-if)# switchport trunk encapsulation dot1q  
Layer3-Switch(config-if)# end
```

! Configure Switch Vlan Interfaces (SVI)

```
Layer3-Switch(config)# interface vlan10  
Layer3-Switch(config-if)# ip address 10.10.10.10 255.255.255.0  
Layer3-Switch(config-if)# no shut
```

```
Layer3-Switch(config)# interface vlan20  
Layer3-Switch(config-if)# ip address 10.20.20.20 255.255.255.0  
Layer3-Switch(config-if)# no shut
```

! Configure default route towards ASA firewall

```
Layer3-Switch(config)# ip route 0.0.0.0 0.0.0.0 10.0.0.2
```

Bijgevoegde bestanden::

Unieke FAQ ID: #1033

Auteur:: diode

Laatst bijgewerkt:22-06-2019 18:15