Ubuntu

Add Private key to Ubuntu server

Generate key with putty key generator

Save the private key

Saving with or whitout Key passphrase

copy the public key from the screen

Make sure there is a .ssh folder in the user/home directory
change to home directory user
cd .ssh
ls

edit the authorized_keys file and paste the public key and save the file
sudo vim authorized_keys

edit the /etc/ssh/sshd_config file
sudo vim /etc/ssh/sshd_config file

Remove the # from
PubkeyAuthentication yes
AuthorizedKeysFile .ssh/authorized_keys .ssh/authorized_keys2

 #PasswordAuthentication yes
and change yes to no
service sshd restart

Add server to Putty

Start Putty and add the conection settings

Ubuntu

Go to connection - SSH - Auth - Credentials and add the private ppk file with browse

Select Session and save the configuration

Click on open to start the session with out password

Unieke FAQ ID: #1189
Auteur: diode
Laatst bijgewerkt:17-05-2024 12:34

URL: https://www.ictweetjes.nl/faq/content/20/190/nl/add-private-key-to-ubuntu-server.html